

Quick Reference Guide 8

Excel 2013 for Windows Keyboard Shortcut Keys



Control Shortcut Keystrokes

Keystroke	Description	
Ctrl + PgDn	Switches between worksheet tabs, from left-to-right.	
Ctrl + PgUp	Switches between worksheet tabs, from right-to-left.	
Ctrl + Shift + &	Applies the outline border to the selected cells.	
Ctrl + Shift_	Removes the outline border from the selected cells.	
Ctrl + Shift + ~	Applies the General number format.	
Ctrl + Shift + \$	Applies the Currency format with two decimal places (negative numbers in parentheses).	
Ctrl + Shift + %	Applies the Percentage format with no decimal places.	
Ctrl + Shift + ^	Applies the Scientific number format with two decimal places.	
Ctrl + Shift + #	Applies the Date format with the day, month, and year.	
Ctrl + Shift + @	l + Shift + @ Applies the Time format with the hour and minute, and AM or PM.	
Ctrl + Shift +!	Applies the Number format with two decimal places, thousands separator, and minus sign (-) for negative values.	
Ctrl + Shift + *	Selects the current region around the active cell (the data area enclosed by blank rows and blank columns). In a PivotTable, it selects the entire PivotTable report.	
Ctrl + Shift + :	Enters the current time.	
Ctrl + Shift + "	Copies the value from the cell above the active cell into the cell or the Formula Bar.	
Ctrl + Shift + Plus (+)	Displays the Insert dialog box to insert blank cells.	
Ctrl + Minus (-)	Displays the Delete dialog box to delete the selected cells.	
Ctrl + ;	Enters the current date.	
Ctrl +`	Alternates between displaying cell values and displaying formulas in the worksheet.	
Ctrl + '	Copies a formula from the cell above the active cell into the cell or the Formula Bar.	
Ctrl + 1	Displays the Format Cells dialog box.	
Ctrl + 2	Applies or removes bold formatting.	
Ctrl + 3	Applies or removes italic formatting.	
Ctrl + 4	Applies or removes underlining.	
Ctrl + 5	Applies or removes strikethrough.	
Ctrl + 6	Alternates between hiding and displaying objects.	
Ctrl + 8	Displays or hides the outline symbols.	
Ctrl + 9	Hides the selected rows.	
Ctrl + 0	Hides the selected columns.	



For software training, contact the Computer Training Center (CTC) at 358-1111 or visit the CTC Web site at http://itcd.hq.nasa.gov/ctc.

Keystroke	Description	
Ctrl + A	Selects the entire worksheet.	
	If the worksheet contains data, Ctrl + A selects the current region. Pressing Ctrl + A a second time selects the entire worksheet.	
	When the insertion point is to the right of a function name in a formula, displays the Function Arguments dialog box.	
	Ctrl + Shift + A inserts the argument names and parentheses when the insertion point is to the right of a function name in a formula.	
Ctrl + B	Applies or removes bold formatting.	
Ctrl + C	Copies the selected cells.	
Ctrl + D	Uses the Fill Down command to copy the contents and format of the topmost cell of a selected range into the cells below.	
Ctrl + E	Adds more values to the active column by using data surrounding that column.	
Ctrl + F	Displays the Find and Replace dialog box, with the Find tab selected.	
	Shift + F5 also displays this tab, while Shift + F4 repeats the last Find action.	
	Ctrl + Shift + F opens the Format Cells dialog box with the Font tab selected.	
Ctrl + G	Displays the Go To dialog box.	
C. 1 W	F5 also displays this dialog box.	
Ctrl + H	Displays the Find and Replace dialog box, with the Replace tab selected.	
Ctrl + I	Applies or removes italic formatting.	
Ctrl + K	Displays the Insert Hyperlink dialog box for new hyperlinks or the Edit Hyperlink dialog box for selected existing hyperlinks.	
Ctrl + L	Displays the Create Table dialog box.	
Ctrl + N	Creates a new, blank workbook.	
Ctrl + 0	Displays the Open dialog box to open or find a file.	
Ct. I. D	Ctrl + Shift + O selects all cells that contain comments.	
Ctrl + P	Displays the Print tab in Microsoft Office Backstage view.	
	Ctrl + Shift + P opens the Format Cells dialog box with the Font tab selected.	
Ctrl + Q	Displays the Quick Analysis options for your data when you have cells that contain that data selected.	
Ctrl + R	Uses the Fill Right command to copy the contents and format of the leftmost cell of a selected range into	
	the cells to the right.	
Ctrl + S	Saves the active file with its current file name, location, and file format.	
Ctrl + T	Displays the Create Table dialog box.	
Ctrl + U	Applies or removes underlining.	
	Ctrl + Shift + U switches between expanding and collapsing of the formula bar.	
Ctrl + V	Inserts the contents of the Clipboard at the insertion point and replaces any selection. Available only after you have cut or copied an object, text, or cell contents.	
	Ctrl + Alt + V displays the Paste Special dialog box. Available only after you have cut or copied an object, text, or cell contents on a worksheet or in another program.	
Ctrl + W	Closes the selected workbook window.	
Ctrl + X	Cuts the selected cells.	
Ctrl + Y	Repeats the last command or action, if possible.	

Keystroke	Description
Ctrl + Z	Uses the Undo command to reverse the last command or to delete the last entry that you typed.

Other Useful Shortcut Keystrokes

Keystroke	Description	
Alt	Displays the Key Tips (new shortcuts) on the ribbon.	
	For example,	
	Alt, W, P switches the worksheet to Page Layout view.	
	Alt, W, L switches the worksheet to Normal view.	
	Alt, W, I switches the worksheet to Page Break Preview view.	
Arrow Keys	Move one cell up, down, left, or right in a worksheet.	
-	Ctrl + Arrow Key moves to the edge of the current data region in a worksheet.	
	Shift + Arrow Key extends the selection of cells by one cell.	
	Ctrl + Shift + Arrow Key extends the selection of cells to the last nonblank cell in the same column or row as the active cell, or if the next cell is blank, extends the selection to the next nonblank cell.	
	Left Arrow or Right Arrow selects the tab to the left or right when the ribbon is selected. When a submenu is open or selected, these arrow keys switch between the main menu and the submenu. When a ribbon tab is selected, these keys navigate the tab buttons.	
	Down Arrow or Up Arrow selects the next or previous command when a menu or submenu is open. When a ribbon tab is selected, these keys navigate up or down the tab group.	
	In a dialog box, arrow keys move between options in an open drop-down list, or between options in a group of options.	
	Down Arrow or Alt + Down Arrow opens a selected drop-down list.	
Backspace	Deletes one character to the left in the Formula Bar.	
	Also clears the content of the active cell.	
	In cell editing mode, it deletes the character to the left of the insertion point.	
Delete	Removes the cell contents (data and formulas) from selected cells without affecting cell formats or comments.	
	In cell editing mode, it deletes the character to the right of the insertion point.	

Keystroke	Description		
End	End turns End mode on or off. In End mode, you can press an arrow key to move to the next nonblank cell		
	in the same column or row as the active cell. End mode turns off automatically after pressing the arro		
	key. Make sure to press End again before pressing the next arrow key. End mode is shown in the statu		
	bar when it is on.		
	If the cells are blank, pressing End followed by an arrow key moves to the last cell in the row or column.		
	End also selects the last command on the menu when a menu or submenu is visible.		
	Ctrl + End moves to the last cell on a worksheet, to the lowest used row of the rightmost used column. If		
	the cursor is in the formula bar, Ctrl + End moves the cursor to the end of the text.		
	Ctrl + Shift + End extends the selection of cells to the last used cell on the worksheet (lower-right corner).		
	If the cursor is in the formula bar, Ctrl + Shift + End selects all text in the formula bar from the cursor		
_	position to the end—this does not affect the height of the formula bar.		
Enter	Completes a cell entry from the cell or the Formula Bar, and selects the cell below (by default).		
	In a data form, it moves to the first field in the next record.		
	Opens a selected menu (press F10 to activate the menu bar) or performs the action for a selected		
	command.		
	In a dialog box, it performs the action for the default command button in the dialog box (the button with		
	the bold outline, often the OK button).		
	Alt + Enter starts a new line in the same cell.		
	Ctrl + Enter fills the selected cell range with the current entry.		
	Shift + Enter completes a cell entry and selects the cell above.		
Esc	Cancels an entry in the cell or Formula Bar.		
LSC	Cancers an entry in the cen of Pornitula Dar.		
	Closes an open menu or submenu, dialog box, or message window.		
	closes an open menu of submenu, dialog box, of message window.		
	It also closes full screen mode when this mode has been applied, and returns to normal screen mode to		
	display the ribbon and status bar again.		
Home	Moves to the beginning of a row in a worksheet.		
	The second committee of a real man a members of		
	Moves to the cell in the upper-left corner of the window when Scroll Lock is turned on.		
	The second of th		
	Selects the first command on the menu when a menu or submenu is visible.		
	Ctrl + Home moves to the beginning of a worksheet.		
	day a money as to the sognitude of a money of		
	Ctrl + Shift + Home extends the selection of cells to the beginning of the worksheet.		
Page	Moves one screen down in a worksheet.		
Down			
	Alt + Page Down moves one screen to the right in a worksheet.		
	Ctrl + Page Down moves to the next sheet in a workbook.		
	Ctrl + Shift + Page Down selects the current and next sheet in a workbook.		
	and a sum of the sum o		

Keystroke	Description
Page Up	Moves one screen up in a worksheet.
	Alt + Page Up moves one screen to the left in a worksheet.
	Ctrl + Page Up moves to the previous sheet in a workbook.
	Ctrl + Shift + Page Up selects the current and previous sheet in a workbook.
Spacebar	In a dialog box, performs the action for the selected button, or selects or clears a check box.
	Ctrl + Spacebar selects an entire column in a worksheet.
	Shift + Spacebar selects an entire row in a worksheet.
	Ctrl + Shift + Spacebar selects the entire worksheet.
	 If the worksheet contains data, Ctrl + Shift + Spacebar selects the current region. Pressing Ctrl + Shift + Spacebar a second time selects the current region and its summary rows. Pressing Ctrl + Shift + Spacebar a third time selects the entire worksheet. When an object is selected, Ctrl + Shift + Spacebar selects all objects on a worksheet.
	Alt + Spacebar displays the Control menu for the Excel window.
Tab	Moves one cell to the right in a worksheet.
	Moves between unlocked cells in a protected worksheet.
	Moves to the next option or option group in a dialog box.
	Shift + Tab moves to the previous cell in a worksheet or the previous option in a dialog box.
	Ctrl + Tab switches to the next tab in dialog box.
	Ctrl + Shift + Tab switches to the previous tab in a dialog box.

Selection Shortcut Keystrokes

Ctrl + Shift + \downarrow selects the entire column of data.	Clicking the column identifier selects entire column.
Ctrl + Shift + \rightarrow selects the entire row of data.	Clicking the row identifier selects entire row.

Ctrl + Shift + End selects an array of data.